BLUEGIGA BLUETOOTH SMART SOFTWARE

RELEASE NOTES

Tuesday, 20 December 2016

Version 4.4



Table of Contents

| 1 | Bluegiga Bluetooth Smart Software - Release Notes | | | 4 |
|---|---|--|-------|---|
| | 1.1 | Changes: 1.5.0 (Build 137) compared to 1.4.2 (Build 130) | · | 4 |
| | 1.2 | Changes: 1.4.2 (Build 130) compared to 1.4.1 (Build 128) | · | 4 |
| | 1.3 | Changes: 1.4.1 (Build 128) compared to 1.4.0 (Build 127) | | 5 |
| | 1.4 | Changes: 1.4.0 (Build 127) compared to 1.3.2 (Build 122) | : | 5 |
| | 1.5 | Changes: 1.3.2 (Build 122) compared to 1.3.1 (Build 119) | | 5 |
| | 1.6 | Changes: 1.3.1 (Build 119) compared to 1.3.1 (Build 118) | | 6 |
| | 1.7 | Changes: 1.3.1 (Build 118) compared to 1.3.0 Beta (Build | 110) | 6 |
| | 1.8 | Changes: 1.3.0 Beta (Build 110) compared to 1.2.2 (Build | 100) | 6 |
| | 1.9 | Changes: 1.2.2 (Build 100) compared to 1.2.1 (Build 91) | | 7 |
| | 1.10 | | | 7 |
| | 1.11 | Changes: 1.2.0 (Build 89) compared to 1.2.0 (Build 88) | · | 7 |
| | 1.12 | Changes: 1.2.0 (Build 88) compared to 1.1.1 (Build 71) | | 8 |
| | 1.13 | Changes: 1.1.1 (Build 71) compared to Beta 2 (Build 55) | | 8 |
| | 1.14 | Changes: 1.1.0 Beta 2 (Build 55) compared to Beta (Buil | d 46) | 9 |
| | | 1.14.1 Known Issues with Build 55 | | 9 |
| | | Changes: 1.1.0 Beta compared to 1.0.3 | | 9 |
| | | Changes: 1.0.3 compared to 1.0.2 | | 9 |
| | | 1.16.1 Memory Limits for 1.0.x | | 9 |
| | 1.17 | Changes: 1.0.2 compared to 1.0.1 | 1 | 0 |
| | 1.18 | Changes: 1.0.1 compared to 1.0.1 | 10 | O |

1 Bluegiga Bluetooth Smart Software - Release Notes

1.1 Changes: 1.5.0 (Build 137) compared to 1.4.2 (Build 130)

Date: December 19th, 2016

New Features

- Added command to enable/disable sleep mode
- Added new command to set pairing distribution keys
- Added support for most recent IAR Embedded Workbench in CSDK installer
- Added non-resolvable address in peripheral privacy mode
- Added non-resolvable address in central privacy mode

Quality Improvements:

- Wake-up pin with state="down" now triggers on correct, falling edge
- Fixed "Device has run out of memory" problem in BLEGUI during OTA update
- PM2 sleep mode now works correctly when both scanning and advertising are enabled
- Timer1 and Timer3 now work correctly when both are activated
- Improved handling disconnection event in sleep mode
- Fixed supervision timeout during slave connection
- Improved enabling slave latency
- Fixed flow control in DFU mode
- Fixed releasing digital pin after ADC use
- Improved cleaning temporary files by BGBuild
- Fixed OTA support for firmware above 96KB
- Fixed sporadic Connection Timeout problem
- · Fixed problem with intermittent disconnects returning "LL Response Timeout" message
- Fixed problem with slow connection when more than 2 devices are connected
- Improved BleUpdate Tool to prevent "Missing license problems"
- · Corrected characteristic length handling
- Fixed low RSSI problem after coming out from PM3 sleep mode
- · Fixed module crash when dim command is used
- Corrected path selections in SDK installer
- · Fixed conflict when Timer1 is used together with SPI
- Fixed problem with scan results delay when slave device is connected with long connection interval
- Fixed problem with OTA flash write on newest iOS (v9.3.4 and above)
- Fixed UART RX glitch during DFU boot
- Fixed problem with still lasting connection after calling end_procedure
- Improved handling attempt to write out of range during DFU in UART and USB mode
- Improved scanning procedure
- Added CSDK OTA template for BLE113-M256
- OTA file is now correctly read from file system in BLEGUI
- Added missing SDK examples for BLE113-M256

1.2 Changes: 1.4.2 (Build 130) compared to 1.4.1 (Build 128)

Date: February 24th, 2016

Quality Improvements:

- read_by_type_req return characteristic handler when error occures
- <pmux regulator_pin="7" /> entry is not obligatory any more for BLE121LR module
- Improved going to low power modes of BLE121LR in CSDK
- Improved DFU over UART, corrected order of parameters in config_hwdata structure for backward compatibility
- Updated CSDK paths to ble-1.4 in IAR templates
- Corrected hardware initialization for OTA and DFU bootloader

- Corrected implementation of OOB_Not_Available error
- Fixed Authentication Requirements error sending
- Fixed problem with OTA for BLE112 module
- Added cleaning of temporary files when BGbuild fails

1.3 Changes: 1.4.1 (Build 128) compared to 1.4.0 (Build 127)

Date: January 19th, 2016

Quality Improvements:

Updated examples with missing <uartboot> entry

1.4 Changes: 1.4.0 (Build 127) compared to 1.3.2 (Build 122)

Date: December 3rd, 2015

New Features

- MAC address change on request added
- Watchdog feature added
- New command ble_cmd_set_initiating_con_parameters added for configuring scanning parameters for Initiating State (establish connection)
- · Added feature which allows to temporarily disable slave latency during runtime
- Updated BLE tools to Qt5 (SDK and BLE GUI Qt libraries)
- Increased maximum BGScript size from ~30KB to 62 KB
- Multiple listeners for a single event in BGScript
- Bluetooth v4.2 specification compliant devices bonding support added

Quality Improvements:

- Persistent store defragmentation improved to prevent data loss
- Fixed some idle state problems
- Fixed problem with RX processing for USB endpoint when received data are less than watermark or data aren't read before receive next packet
- Fixed problem with sending 64 or more bytes to USB endpoint
- Fixed problem with Dongle hang when running flash_ps_dump over USB
- Improved script execution speed
- Fixed problem with calculating maximum characteristics limitation for user characteristics
- Fixed problem with DFU update using USB 3.0
- BGBuild now correctly returns error if user data exceeds the maximum size
- Fixed problem with slow connection speed, when master was already connected with a long connection interval
- Fixed problem with LL_CHANNEL_MAP_REQ confirmation to master
- New attribute <uartboot> added, to fix problem with BgScript when UART dfu bootloader is used

1.5 Changes: 1.3.2 (Build 122) compared to 1.3.1 (Build 119)

Date: December 29th, 2014

Quality Improvements:

- PS keys are defragmented in case PS key save fails in order to overcome the possible issue with frequent PS key saving
- Connection reliability is improved when large slave latency values are used
- Improved reliability of connection establishment
- Fixed an issue that caused the firmware to hang when directed connectable mode was canceled before advertising timeout occurs
- Improved the reliability of advertising in three different channels when advertising and scanning are used simultaneously.

Silicon Labs Page 5 of 11

- Temperature calibration improved and thus improving the stability of the TX power for BLE121LR
- Configuring Port 2 over API does not not anymore cause resetting Port 0/1.
- I2C pin states retained when sleeping
- Boot event is always generated when entering DFU mode.
- Chaining BGScript events has been enabled
- Binary shift left operator fixed
- · C-SDK templates and environment configurations improved
- BLE SW Update Tool updated to preserve the temperature calibration value

1.6 Changes: 1.3.1 (Build 119) compared to 1.3.1 (Build 118)

Date: September 10th, 2014

Quality Improvements:

Analog comparator interrupt fixed

1.7 Changes: 1.3.1 (Build 118) compared to 1.3.0 Beta (Build 110)

Date: September 2nd, 2014

Note: Release 1.3.1 Build 118 is the first mass production version for *Bluetooth* Smart Software v.1.3 with BLE121LR Module

New Features

- New Send Attribute API command added for controlling the notifications and indications.
- New Whitelist Bonds API command added which adds the bonded devices to the white list.
- A new configuration options added into the config.xml file, which can be used to disable DFU updates.

Quality Improvements:

- I/O interrupt handler updated to avoid overflow of the I/O interrupts. The change allows only one I/O interrupt for each port to be queued by disabling the port interrupt until the corresponding I/O interrupt event is generated.
- Interrupt handling improved when reading the internal temperature sensor and unnecessary interrupts events will not occur any more.
- Writing to the end of user data region in the flash is fixed.
- UART priority adjusted to improve UART reliability under high load for example when encrypted Bluetooth connections are used.
- TX power control fixed for BLE121LR Bluetooth Smart Long Range Module.
- Reliability of *Get Bonds* API command improved.
- An error event is returned if the encryption key is not present locally and a remote device tries to make a
 pairing using an old encryption key.
- Interoperability improvements with Windows Phone 8.1, LG D802 model, and with some un-compliant iBeacon implementations
- C SDK environment now supports BLE121LR Bluetooth Smart Long Range module.
- OTA DFU script and example improved for BLE121LR *Bluetooth* Smart Long Range module.

1.8 Changes: 1.3.0 Beta (Build 110) compared to 1.2.2 (Build 100)

Date: May 20th, 2014

Note: Release 1.3.0 Build 110 is a beta release for BLE 1.3 SW and BLE121LR Module

New Features

- Bluetooth Smart software now supports the new BLE121LR hardware
- BLE Software Update tool now also support the new BLE121LR hardware

Silicon Labs Page 6 of 11

- SDK examples haven been updated and restructured to support the BLE121LR and the new DKBLE development kit
- New API command added for turning On/Off USB Interface on BLE112
- New API command added to access the AES128 hardware encryption engine
- New API command added to reduce the RX sensitivity and shorten the range.
- OTA firmware update now supports just upgrading the BGScript application and GATT database
 - ~90% smaller firmware file and faster and lower power OTA updates
 - Enables OTA update on the hardware variants that only have 128kB flash

Quality Improvements:

- In BGAPI packet mode the length checks have been added and too short or long BGAPI packet will
 produce an error
- Advertising mode (scannable and non-connectable) while connected to an other device enabled
- Enhancements made to BGScript engine that allow more efficient use of RAM

1.9 Changes: 1.2.2 (Build 100) compared to 1.2.1 (Build 91)

Date: Feb 16th, 2014

New Features

- Added the support of BLE113 with the internal 256kB flash memory
- Added software support for Over-the-Air (OTA) firmware update for the internal 256kB memory
- Added support for SPI interface and pin selection for external SPI flash to be used with OTA updates.
- Added a compiler option to generate a separate firmware file for OTA firmware updates
- Added APIs for reading (Read Data), writing (Write Data), and erasing (Erase Page) the user area data
 on the internal flash memory
- Added APIs for handling I/O port interrupts (Io Port Irq Enable) and setting the directions (Io Port Irq Direction)
- Added API's for handling the comparator functionality under HW commands and events.
- Added testing APIs for sending and receiving data (Phy Tx, Phy Rx, Phy End) for Bluetooth testing purposes
- BGScript code can now be split into multiple files with the new IMPORT and EXPORT directives.

Quality Improvements:

- OTA firmware update reliability improved
- BGScript fixed when sign extensions are used
- Bonding robustness improved in the cases when encrypted link in use

1.10 Changes: 1.2.1 (Build 91) compared to 1.2.0 (Build 89)

Date: October 25th, 2013

Quality Improvements:

- Interoperability improvements, which make paring and connection establishment more reliable with new Android devices supporting *Bluetooth* Smart.
- Enhanced broadcasting improved and connection reliability improved for devices that are in reliable advertisement mode.
- BGBuild compiler will now produce errors if BGScript variables use reserved names.
- BLE Update tool's Windows compatibility improved.

1.11 Changes: 1.2.0 (Build 89) compared to 1.2.0 (Build 88)

Date: October 14th, 2013

Improvements:

Silicon Labs Page 7 of 11

CC debugger drivers now included in the Bluetooth Smart Software and SDK installation package.

1.12 Changes: 1.2.0 (Build 88) compared to 1.1.1 (Build 71)

Date: September 26th, 2013

New Features

- Production quality firmware for BLE113 Bluetooth Smart Module.
- Enhanced Broadcasting added, so a peripheral device is able to check whether advertisements are received by a master device.
- Both non-connectible advertising and active/passive scanning without ability to connect, enabled at the same time, are now possible for a slave during a connection. When connected and in master mode, active/passive scanning with ability to connect is additionally possible, for the master to be able to connect to multiple slaves.
- Security: Fixed passkey support added for bonding. A fixed six digit passkey can be pre-determined and then used during the bonding procedure.
- DFU: Over-the-Air (OTA) firmware upgrade feature added to enable wireless software updates. Requires additional flash, such as an external 128 kB flash memory module connected via SPI.
- DFU: DFU over UART feature added.
- BGScript: BGScript applications can now use functions (procedures). memset() functionality added.
- BGAPI: Added new commands to investigate the RF channel quality (RSSI) or by measuring packet loss during a connection.
- BGAPI: Validation of BGAPI commands added, BGAPI protocol produces errors for invalid or incomplete BGAPI commands sent by a host.
- BGAPI: New event is added which is generated when a bonding is attempted but the bonding list is already full.
- BLEGUI: DFU over UART, USB or OTA can now be done using BLEGUI.
- SDK: Beta-level C-language libraries and IAR Embedded Workbench for 8051 compatible SDK is now available via special request.
- SDK: Bluetooth Smart SDK comes now as a self-installing executable, including BLE Update firmware flashing tool.

Quality Improvements:

- BLE113 software has reached production quality, improving power consumption and connection timing.
- Defragmenting of flash memory is enabled by default.
- USB functionality (BLE112 and BLED112) made more robust in general and when USB 3.0 ports are used.
- Robustness improvements done for advertising, scanning, and connections.

1.13 Changes: 1.1.1 (Build 71) compared to Beta 2 (Build 55)

- This is the the official 1.1.0 build for BLE112 and BLED112 modules. Bluegiga license key is required in the module, and if it is missing, it needs to be applied with BLE Update via the CC debug programming pins.
- BLE113 support added. SW is not considered yet to be fully qualified for BLE113, and the possible changes and improvement for BLE113 will still take place.
- Few semantics changes for command, the set_txpower command uses range 0-15. timer behaviour improvement - Cancelling previous timer if new repeating timer is added,
- Various improvements and fixes from multi-connection features, e.g., connection interval desgined be in range 2.5*max_connections, reliability improved up to 8 simultaneous connections,
- Multiple quality improvements, e.g., validating supervision time-out when connecting, connection
 reliability with slave latency improved, de-fragmenting PS store at boot-up, watermarks working properly
 over USB too, fixing issue with too short SW timer, robustness improvement related to scanning and
 connection establishments
- PC GUI SW improved E.g., logview clearing, performance improved when long log traced

1.14 Changes: 1.1.0 Beta 2 (Build 55) compared to Beta (Build 46)

- Packet mode option added for easing up the flow control when using BGAPI over UART (See hardware. xml/usart)
- Throughtput options added for higher throughput (See config.xml/throughput)
- BG Script performance improved for having the faster scripts
- BG Script watchdog timer added (See config.xml/script timeout)
- Cable Replacement iPhone reference implementation included (a separate Zip file at Tech Foum)
- New BLE SW update tool for BLE SW (a separate zip at Tech Forum), this is to be used instead TI SW update tool (SmartRF).
- User Read Response and User Write Response API's implemented.
- Various fixes done based on the feedback to Beta build (e.g, script functions like memcmp, I2C functionality)

Note: Final 1.1.0 SW release will require a Bluegiga license key in the module, and this will need to be applied with BLE Update via the CC debug programming pins..

1.14.1 Known Issues with Build 55

- Multi-connection (master mode) is not fully stable in highly stressed use cases
- Calling system_endpoint_tx command multiple times in a row can crash the script
- C examples with BGLib not yet make compatible with 1.1.0 SW.

1.15 Changes: 1.1.0 Beta compared to 1.0.3

- Multi-connection support added to the master side (i.e., central). Verified up to 4 simultaneous connections.
- API's supporting the cable replacement use case, e.g., for enabling E2E flow control
- Chipset's PWM capability accessible via BGAPI.
- BGAPI changes for I2C usage
- Multiple new BG script features such as logical AND, WHILE loop, bit shifting.
- Flexible build-time memory management added, e.g., removing BGscript size limitation when operating with the available flash memory size
- Several smaller improvements for quality and stability.

Note: Final 1.1.0 SW release will require the Bluegiga license key at the module and this will need to be entered to the modules through the programming pins.

1.16 Changes: 1.0.3 compared to 1.0.2

- BGScript activation for BLED112 fixed.
- SetScanParameter (related to scanning window) relialibility improved.
- Transitions to PM3 (power mode 3) improved for decreasing unnecessary power consumption.

1.16.1 Memory Limits for 1.0.x

- Combined GATT database and BGScript size is limited to 2KB flash
- 256 bytes is reserved for script buffers and variables
- 2KB GATT attribute values stored in ram
- PS Store size is 14KB

Note: These limitations are not applicable as such to 1.1.x SW branch where the flexible build-time memory management is supported.

1.17 Changes: 1.0.2 compared to 1.0.1

- Commands returning variable length data works in BGScript.
- ADC functionality fixed if using analog pin as reference.

1.18 Changes: 1.0.1 compared to 1.0.1

- SW is also released through Bluegiga tech forum
- Few final fixes done.





loT Portfolio www.silabs.com/loT



SW/HWwww.silabs.com/simplicity



Quality www.silabs.com/quality



Support and Community community.silabs.com

Disclaimer

Silicon Labs intends to provide customers with the latest, accurate, and in-depth documentation of all peripherals and modules available for system and software implementers using or intending to use the Silicon Labs products. Characterization data, available modules and peripherals, memory sizes and memory addresses refer to each specific device, and "Typical" parameters provided can and do vary in different applications. Application examples described herein are for illustrative purposes only. Silicon Labs reserves the right to make changes without further notice and limitation to product information, specifications, and descriptions herein, and does not give warranties as to the accuracy or completeness of the included information. Silicon Labs shall have no liability for the consequences of use of the information supplied herein. This document does not imply or express copyright licenses granted hereunder to design or fabricate any integrated circuits. The products are not designed or authorized to be used within any Life Support System without the specific written consent of Silicon Labs. A "Life Support System" is any product or system intended to support or sustain life and/or health, which, if it fails, can be reasonably expected to result in significant personal injury or death. Silicon Labs products are not designed or authorized for military applications. Silicon Labs products shall under no circumstances be used in weapons of mass destruction including (but not limited to) nuclear, biological or chemical weapons, or missiles capable of delivering such weapons.

Trademark Information

Silicon Laboratories Inc.®, Silicon Laboratories®, Silicon Labs®, Silabs® and the Silicon Labs logo®, Bluegiga®, Bluegiga®, Bluegiga Logo®, Clockbuilder®, CMEMS®, DSPLL®, EFM®, EFM32®, EFR, Ember®, Energy Micro, Energy Micro logo and combinations thereof, "the world's most energy friendly microcontrollers", Ember®, EZRadio®, EZRadio®, EZRadio®, Gecko®, ISOmodem®, Precision32®, ProSLIC®, Simplicity Studio®, SiPHY®, Telegesis, the Telegesis Logo®, USBXpress® and others are trademarks or registered trademarks of Silicon Labs. ARM, CORTEX, Cortex-M3 and THUMB are trademarks or registered trademarks of ARM Holdings. Keil is a registered trademark of ARM Limited. All other products or brand names mentioned herein are trademarks of their respective holders.



Silicon Laboratories Inc. 400 West Cesar Chavez Austin, TX 78701 USA